

Updating the Main Page Slideshow

From the Wordpress dashboard, choose **The7 Slider Revolution**.


Slider in use is **#19 homepage-top1**. Click to open.

This slideshow is a single slide with many layers that display in a specific order and timing. The order is based on where the layer's slider bar falls along the timeline, which is represented in seconds from left to right.

We will add and remove layers, and adjust the timing and actions for layers as needed.

Remove expired events:

Find the layer you need to remove - click on the **layer names** to display stacked layers.



The selected layer will show in the slider preview:




You can see which layer is active because the **resize handles** will be visible.
Press the delete key and confirm.

You will need to adjust the timing of the remaining layers using the slider bar to the right of each image. The first image should enter at approximately the same time as the **iPad** layer. **NOTE: Do this step after you've added any new event images.**

Add new events

Click the add layer button, and choose "image" from the drop-down menu.



Add the new image through the media library. The new image will appear at the **bottom** of the list of layers.

Adjust the Layer Order


You can adjust the layer order and timing without reordering the list, but it's easier to adjust the timing if you see the layers listed in order.

- Reorder layers by clicking and dragging the **layer numbers**.
- Layers should be configured so that they appear in date order

Adjust the Layer Timing


Timing is based on the position and length of **the slider bar**.

- The darker grey (red when layer is selected) section is the duration of the entry animation.
- The lighter grey section is the total display time. Leaving the layers to display until the end is fine, since the course promotion layers that appear on the iPad are stacked.




Adjust the Layer Attributes

Fix the way the layer comes into view and what happens when the layer is clicked.



- Ensure the **layer** is selected.
- Choose the **animation** tab. The entry animation should be SlideMaskFromRight; default timing is fine. No exit animation is required.
- Choose the **actions** tab. This makes the slide clickable to go to the event listing:




Add an action with settings as above. Use the full URL of the event listing.


Adjust the Image Display Size and Position



- **Select the layer.** If it's not visible (behind other layers), you can click on the layer name in the timing list to select it. The selected layer will show resize handles.
- **Resize and reposition** the layer using the controls on the top right of the preview window in the **STYLE** tab, as below:



Repeat the display size and positioning adjustment for each of the display modes:



Settings should be as follows:

	X	Y	W	H
Monitor	426	121	420	315
Laptop	426	121	420	315
Tablet	230	75	326	245
Smartphone	140	12	326	245

Save the slideshow:

Click the green SAVE button.

